



Brian E. Whipker¹



Josh Henry¹



W. Garrett Owen²

Volume 1 Number #8 February 2018

Nutritional Monitoring Series

Hydrangea - Blue Sepals (*Hydrangea macrophylla*)

Fertilization practices and substrate pH levels must be customized for growing blue or pink colored florist hydrangeas. Hydrangeas require low levels of fertilization, growing optimally with 100 to 150 ppm N. For blue hydrangeas, maintain substrate pH values between 5.2 and 5.5. In order to deepen the blue coloration of the sepals, the substrate pH must be maintained below 5.5 and specialized fertilization practices need to be followed (see e-GRO Alert 6.04). In addition, hydrangeas are susceptible to high pH disorders, developing iron (Fe) deficiency when the pH exceeds 6.5.



Funding Generations of Progress
Through Research and Scholarships



Project Sponsor



Figure 1. Low soluble salts [referred to as electrical conductivity (EC)] can result in lower leaf yellowing (chlorosis).

© Brian E. Whipker

Blue Sepal
Hydrangea

Target Nutrition Parameters

pH Category I:
5.2 to 5.5

Fertility Category:
Low
100 to 150 ppm N

EC Category A:
1:2 Extraction:
0.4 to 0.6 mS/cm

SME:
0.9 to 1.3 mS/cm

PourThru:
1.3 to 2.0 mS/cm

www.fertdirtandsquirt.com

¹NC State University
bwhipker@ncsu.edu

²Michigan State University
wgowen@msu.edu



Figure 2. Low soluble salts [referred to as electrical conductivity (EC)] can also result in lower leaf reddening.



Figure 3. High soluble salts [referred to as electrical conductivity (EC)] due to an over-application of aluminum sulfate can lead to marginal leaf browning and death (necrosis).

Fertility Management of Blue Hydrangeas

Hydrangeas require a low level of fertility. Growers should maintain fertilization at 100 to 150 ppm N. Low soluble salts [referred to as electrical conductivity (EC)] can cause yellowing (chlorosis) (Fig. 1) or reddening (Fig. 2) on the lower foliage. High EC can lead to marginal chlorosis or browning (necrosis) of the lower leaves (Fig. 3). If the EC increases beyond optimal levels, apply a few irrigations with clear water to lower it. If the EC is excessively high, apply two clear water irrigations to leach excess salts (but this more drastic step results in wasting your fertilizer investment and can be avoided by monitoring the EC and taking action before it becomes excessive).

Substrate pH should be maintained between 5.2 and 5.5. Lower or higher values beyond this range may lead to low or high pH induced nutritional disorders (Landis and Whipker, 2017). High pH inhibits iron (Fe) uptake, causing interveinal chlorosis of the upper foliage (Fig. 4). Iron deficiency can be remedied with an application of iron chelate. Low pH causes excessive uptake of Fe and manganese (Mn), which can lead to toxicity symptom development. Iron and Mn toxicity can be remedied by a flowable lime application to adjust (raise) the pH.

Summary

Maintaining a low level of fertility at 100 to 150 ppm N and a pH of 5.2 to 5.5 should enable you to grow healthy blue hydrangeas (Fig. 5) while preventing nutritional disorders.



We appreciate the grant support of the Fred C. Gloeckner Foundation for the NC State University Research on targeting critical tissue aluminum levels in hydrangeas.

Literature Cited

Bailey, D.A. 1989. Hydrangea production. Timber Press Growers Handbook series 3. Portland, OR.

Bryson, G.M., H.A. Mills, D.N. Sasseville, J.B. Jones, Jr., and A.V. Barker. 2014. Plant analysis handbook III. Micro-Macro Publishing, Inc., Athens, GA.

Landis, H. and B.E. Whipker. 2017. Nutrient management strategies for ensuring blue coloration of greenhouse hydrangeas. e-GRO Alert 6-04, p. 6.



Figure 4. High substrate pH leads to interveinal yellowing (chlorosis) on the upper foliage.

Table 1. Recommended range of leaf tissue analysis for hydrangea (*Hydrangea macrophylla*).

Element	Sufficiency range ¹	Nutrient levels when deficiency symptoms appear ²
Nitrogen (%)	2.24 – 5.60	≤1.50
Phosphorus (%)	0.25 – 0.70	≤0.20
Potassium (%)	2.20 – 7.80	≤1.00
Calcium (%)	0.60 – 2.00	≤0.60
Magnesium (%)	0.22 – 0.61	≤0.08
Sulfur (%)	0.20 – 0.70	NR ³
Iron (ppm)	50 – 300	≤60
Manganese (ppm)	38 – 300	≤8
Zinc (ppm)	20 – 200	≤20
Copper (ppm)	1 – 25	≤4
Boron (ppm)	20 – 50	2≤5
Molybdenum (ppm)	0.09 – 0.22	≤1

¹ Source: Bryson et al. (2014). Note: No color type was specified in the data.

² Source: Bailey (1989), based on the cultivar ‘Rose Supreme’

³ NR = not reported



Figure 5. Blue coloration of hydrangea sepals is the result of maintaining the substrate pH below 5.5, providing aluminum, and following fertilization practices that enhance aluminum uptake. Mike Renfrow of Cyn-Mar Greenhouse in Pine Level, NC shows off his crop.

Corrective Procedures for Modifying Substrate pH and Electrical Conductivity (EC)

When the pH or substrate electrical conductivity (EC) drifts into unwanted territory, adjustments must be made. Below are the standard corrective procedures used to modify the substrate pH and EC for greenhouse grown crops in soilless substrates.

1. Low Substrate pH Correction

When Fe and Mn toxicity becomes a problem, adjust (raising) substrate pH to the recommended pH range. Corrective procedures to raise low pH levels are listed below. Switching to a basic fertilizer when the substrate pH is nearing the lower limit will help stabilize the pH. If the pH is below the recommended range, then corrective procedures will need to be implemented. Flowable lime is one option. Using a rate of 2 quarts per 100 gallons of water will typically increase the substrate pH by roughly 0.5 pH units. Two quarts can be used through an injector. Additional applications can be made if needed. Potassium bicarbonate (KHCO_3) can also be applied. A rate of 2 pounds per 100 gallons of water will increase the substrate pH by roughly 0.8 pH units. This treatment will also provide excessive potassium (K) and cause a spike in the substrate EC. A leaching irrigation with clear water is required the following day to restore the nutrient balance (the ratio of K:Ca:Mg) and lower the EC. As always, remember to recheck your substrate pH to determine if reapplications are needed.

pH Adjustment Recommendations

Flowable Lime

- Use 1 to 2 quarts per 100 gallons of water.
Rinse foliage.
- Avoid damage to your injector by using rates of 2 quarts per 100 gallons of water, or less.
- Can split applications.

Hydrated Lime

- Mix 1 pound in 3 to 5 gallons of WARM water. Mix twice. Let settle. Decant liquid and apply through injector at 1:15.
- Caustic (rinse foliage ASAP and avoid skin contact)

Potassium Bicarbonate (KHCO_3)

- Use 2 pounds per 100 gallons of water
- Rinse foliage immediately.
- Provides 933 ppm K.
- Leach heavily the following day with a complete fertilizer to reduce substrate EC and restore nutrient balance.
- Rates greater than 2 pounds per 100 gallons of water can cause phytotoxicity!

2. High Substrate pH Correction

The target pH for many species is between 5.8 and 6.2. Higher pH values will result in Fe deficiency and lead to the development of interveinal chlorosis on the upper leaves. Check the substrate pH to determine if it is too high. Be careful when lowering the substrate pH, because going too low can be much more problematic and difficult to deal with.

Acid-based Fertilizer

If the substrate pH is just beginning to increase, then first consider switching to an acidic-based fertilizer. These ammoniacal-nitrogen (N) based fertilizers are naturally acidic and plant nitrogen uptake will help moderate the substrate pH over a week or two.

Acid Water Drench

Some growers use this intermediate correction if pH levels are not excessively high and a quick lower of the substrate pH is desired. Use sulfuric acid to acidify your irrigation water to a pH 4.0 to 4.5. Apply this acid water as a substrate drench providing 5 to 10% excessive leaching of the substrate. Rinse the foliage to avoid phytotoxicity. Results should be visible within 5 days. Retest the substrate pH and repeat if needed.

Iron Drench

If the levels are excessively high, then an Fe chelate application can be made to the substrate.

Below are the options.

Iron Chelate Drench (options)

- Iron-EDDHA: mix 5 ounces in 100 gallons of water
- Iron-DTPA: mix 5 ounces in 100 gallons of water
- Iron sulfate: mix 4-8 ounces in 100 gallons of water
- Apply as a substrate drench with sufficient volume to leach the pot.
- Rinse foliage immediately.
- Avoid use on iron efficient plants (geraniums).

3. Low EC Correction

If low EC problems occur, increase the fertilization rate to 300 ppm N for a few applications before returning to the recommend fertilization rate for the crop.

4. High EC Correction

Excessively high fertilization rates will result in a marginal leaf burn. Check the substrate EC to confirm your diagnosis. Values greater than 6.0 mS/cm based on the PourThru sampling method can be problematic for many plants.

Switch to Clear Water Irrigations

If the substrate EC is just beginning to increase over time, then leach with a few clear water irrigations to lower EC levels by flushing out the salts.

Clear Water Leaching

If the EC values are excessively high, leach the substrate twice with back-to-back clear water irrigations. Then allow the substrate to dry down normally before retesting the EC. If EC levels are still too high, repeat the double leach. Once the substrate EC is back within the normal range, use a balanced fertilizer at a rate of 150 to 200 ppm N.



e-GRO Alert

www.e-gro.org

CONTRIBUTORS

Dr. Nora Catlin
Floriculture Specialist
Cornell Cooperative Extension
Suffolk County
nora_catlin@cornell.edu

Dr. Chris Currey
Assistant Professor of Floriculture
Iowa State University
ccurrey@iastate.edu

Dr. Ryan Dickson
Extension Specialist for Greenhouse
Management & Technologies
University of New Hampshire
ryan.dickson@unh.edu

Thomas Ford
Commercial Horticulture Educator
Penn State Extension
tf7@psu.edu

Dan Gilrein
Entomology Specialist
Cornell Cooperative Extension
Suffolk County
dog1@cornell.edu

Dr. Joyce Latimer
Floriculture Extension & Research
Virginia Tech
jlatime@vt.edu

Heidi Lindberg
Floriculture Extension Educator
Michigan State University
wolleage@anr.msu.edu

Dr. Roberto Lopez
Floriculture Extension & Research
Michigan State University
rlopez@msu.edu

Dr. Neil Mattson
Greenhouse Research & Extension
Cornell University
neil.mattson@cornell.edu

Dr. W. Garrett Owen
Floriculture Outreach Specialist
Michigan State University
wgowen@msu.edu

Dr. Rosa E. Raudales
Greenhouse Extension Specialist
University of Connecticut
rosa.raudales@uconn.edu

Dr. Beth Scheckelhoff
Extension Educator - Greenhouse Systems
The Ohio State University
scheckelhoff.11@osu.edu

Lee Stivers
Extension Educator - Horticulture
Penn State Extension
Washington County
ljs32@psu.edu

Dr. Paul Thomas
Floriculture Extension & Research
University of Georgia
palthomas@uga.edu


Dr. Ariana Torres-Bravo
Horticulture / Ag. Economics
Purdue University
torres2@purdue.edu

Dr. Brian Whipker
Floriculture Extension & Research
NC State University
bwhipker@ncsu.edu

Copyright © 2018

Where trade names, proprietary products, or specific equipment are listed, no discrimination is intended and no endorsement, guarantee or warranty is implied by the authors, universities or associations.

Cooperating Universities



Cornell University

**Cornell Cooperative Extension
Suffolk County**



**University of
New Hampshire**
Cooperative Extension

PENN STATE



Cooperative Extension
College of Agricultural Sciences



**MICHIGAN STATE
UNIVERSITY**

UCONN

**PURDUE
UNIVERSITY**



The University of Georgia



**THE OHIO STATE
UNIVERSITY**

**NC STATE
UNIVERSITY**

IOWA STATE UNIVERSITY

In cooperation with our local and state greenhouse organizations



Metro Detroit Flower Growers Association

