



Brian E. Whipker<sup>1</sup>



W. Garrett Owen<sup>2</sup>

Volume 4 Number 2 May 2021

## Nutritional Monitoring Series

# *Clerodendrum*

(*Clerodendrum thomsoniae*)


Clerodendrum require medium fertility levels between 150 to 200 ppm N. Optimal substrate pH values range from 5.8 to 6.2. Substrate pH values above 6.5 inhibit Fe availability and induce interveinal chlorosis (yellowing) of the recently matured leaves. Low substrate electrical (EC) conductivity levels will result in stunted plant growth, lower leaf chlorosis, and leaf loss. Excessive EC levels will result in lower leaf marginal necrosis (death).



Funding Generations of Progress  
Through Research and Scholarships



Project Sponsor



© Brian Whipker

Figure 1. Substrate pH above 6.5 or over can inhibit iron (Fe) uptake causing newly developed clerodendrum (*Clerodendrum thomsoniae*) leaves to become Fe-deficient and exhibit interveinal chlorosis (yellowing).

### Target Nutrition Parameters

**pH Category III:**

5.8 to 6.2

**Fertility Category:**

Medium

150 - 200 ppm N

**EC Category B:**

1:2 Extraction:

0.6 to 0.9 mS/cm

**SME:**

0.1.3 to 2.0 mS/cm

**PourThru:**

2.0 to 3.0 mS/cm

Clerodendrum

<sup>1</sup>NC State University  
bwhipker@ncsu.edu

<sup>2</sup>University of Kentucky  
wgowen@uky.edu



Figure 2. A top view of a clerodendrum (*Clerodendrum thomsoniae*) plant exhibiting advanced interveinal chlorosis (yellowing) on the newly expanding and growing leaves. Photo by: Brian Whipker.

### Fertility Management of Clerodendrum

Clerodendrums should be grown with a pH range of 5.8 to 6.2. High substrate pH above 6.3 can inhibit Fe uptake causing newly expanding leaves to develop interveinal chlorosis (Koranski, 1976; Figs. 1 and 2). Corrective procedures for high substrate pH should begin within the range of 6.3 to 6.5. Low substrate pH below 5.0 can result in lower leaf bronzing (Fig. 3).

Use recommended 1:2 Extraction, SME, or PourThru methods to determine and monitor substrate pH and soluble salts [referred to as electrical conductivity (EC)] values. Additionally, conduct routine foliar analysis tests to monitor crop nutrient status. Tissue nutrient levels found in healthy, newly expanded leaves of clerodendrum (Davis et al., 2011) are listed in Table 1. Monitoring substrate pH and nutrient status will enable growers to avoid pH-induced nutritional disorders.

Providing medium fertility of 150 to 200 ppm N is recommended during the vegetative growth phase (Beck, 1975). Insufficient fertility levels (low EC) will result in stunted growth and lower leaf pale coloration and chlorosis (Fig. 4). Leaf loss also occurs with advanced symptomology.

High EC can cause stunted plant growth and lower leaf necrosis (Fig. 5). Routinely check substrate EC and maintain below 0.9, 2.0, or 3.0 mS/cm, based on the 1:2 Extraction, SME, or PourThru methods, respectively.



### Summary

Providing clerodendrums with a moderate level of fertility ranging from 150 to 200 ppm N and maintaining a substrate pH of 5.8 to 6.2 will prevent most nutritional disorders from occurring.

### Literature Cited

Beck, G.E. 1975. Preliminary suggestions for the culture and production of clerodendrum. Ohio Florists' Association Bulletin. 547:6-7.

Davis, K.I., C.E. Niedziela Jr., M.R. Reddy, B.E. Whipker, and J.M. Frantz. 2011. Nutrient disorders symptomology and foliar concentrations of *Clerodendrum thomsoniae* J. of Plant Nutrition. 34:7, 1079-1086, DOI: 10.1080/01904167.2011.555805

Koranski, D.S. 1976. Growth and flowering of *Clerodendrum thomsoniae* Balif. PhD Dissertation, University of Wisconsin, Madison, WI, USA.



© Brian Whipker

Figure 3. Bronzing of clerodendrum (*Clerodendrum thomsoniae*) lower leaves occurs when the substrate pH is below 5.0. Photo by: Brian Whipker.



© Brian Whipker

Figure 4. Providing insufficient fertility [low electrical conductivity (EC)] during clerodendrum (*Clerodendrum thomsoniae*) production can result in lower leaf chlorosis (yellowing). Photo by: Brian Whipker.

Table 1. Leaf tissue nutrient sufficiency range for clerodendrum (*Clerodendrum thomsoniae*) grown hydroponically with a modified, complete, Hoagland’s fertilizer solution.

| Element        |       | Reference Range |
|----------------|-------|-----------------|
| Nitrogen (N)   | (%)   | 3.53            |
| Phosphorus (P) |       | 0.93            |
| Potassium (K)  |       | 3.68            |
| Calcium (Ca)   |       | 2.32            |
| Magnesium (Mg) |       | 0.52            |
| Sulfur (S)     |       | 0.44            |
| Iron (Fe)      | (ppm) | 114.2           |
| Manganese (Mn) |       | 219.5           |
| Zinc (Zn)      |       | 9.1             |
| Copper (Cu)    |       | 7.9             |
| Boron (B)      |       | 21.6            |

Source: Davis et al., (2011)



Figure 5. Excessive fertility [high electrical conductivity (EC)] during clerodendrum (*Clerodendrum thomsoniae*) production can cause stunted growth and lower leaf marginal necrosis (death). Photo by: Brian Whipker.

## Corrective Procedures for Modifying Substrate pH and Electrical Conductivity (EC)

When the pH or substrate electrical conductivity (EC) drifts into unwanted territory, adjustments must be made. Below are the standard corrective procedures used to modify the substrate pH and EC for greenhouse grown crops in soilless substrates.

### 1. Low Substrate pH Correction

When Fe and Mn toxicity becomes a problem, adjust (raising) substrate pH to the recommended pH range. Corrective procedures to raise low pH levels are listed below. Switching to a basic fertilizer when the substrate pH is nearing the lower limit will help stabilize the pH. If the pH is below the recommended range, then corrective procedures will need to be implemented. Flowable lime is one option. Using a rate of 2 quarts per 100 gallons of water will typically increase the substrate pH by roughly 0.5 pH units. Two quarts can be used through an injector. Additional applications can be made if needed. Potassium bicarbonate ( $\text{KHCO}_3$ ) can also be applied. A rate of 2 pounds per 100 gallons of water will increase the substrate pH by roughly 0.8 pH units. This treatment will also provide excessive potassium (K) and cause a spike in the substrate EC. A leaching irrigation with clear water is required the following day to restore the nutrient balance (the ratio of K:Ca:Mg) and lower the EC. As always, remember to recheck your substrate pH to determine if reapplications are needed.

## pH Adjustment Recommendations

### *Flowable Lime*

- Use 1 to 2 quarts per 100 gallons of water.  
Rinse foliage.
- Avoid damage to your injector by using rates of 2 quarts per 100 gallons of water, or less.
- Can split applications.

### *Hydrated Lime*

- Mix 1 pound in 3 to 5 gallons of WARM water. Mix twice. Let settle. Decant liquid and apply through injector at 1:15.
- Caustic (rinse foliage ASAP and avoid skin contact)

### *Potassium Bicarbonate ( $\text{KHCO}_3$ )*

- Use 2 pounds per 100 gallons of water
- Rinse foliage immediately.
- Provides 933 ppm K.
- Leach heavily the following day with a complete fertilizer to reduce substrate EC and restore nutrient balance.
- Rates greater than 2 pounds per 100 gallons of water can cause phytotoxicity!

### 2. High Substrate pH Correction

The target pH for many species is between 5.8 and 6.2. Higher pH values will result in Fe deficiency and lead to the development of interveinal chlorosis on the upper leaves. Check the substrate pH to determine if it is too high. Be careful when lowering the substrate pH, because going too low can be much more problematic and difficult to deal with.



### *Acid-based Fertilizer*

If the substrate pH is just beginning to increase, then first consider switching to an acidic-based fertilizer. These ammoniacal-nitrogen (N) based fertilizers are naturally acidic and plant nitrogen uptake will help moderate the substrate pH over a week or two.

### *Acid Water Drench*

Some growers use this intermediate correction if pH levels are not excessively high, and a quick lower of the substrate pH is desired. Use sulfuric acid to acidify your irrigation water to a pH 4.0 to 4.5. Apply this acid water as a substrate drench providing 5 to 10% excessive leaching of the substrate. Rinse the foliage to avoid phytotoxicity. Results should be visible within 5 days. Retest the substrate pH and repeat if needed.

### *Iron Drench*

If the levels are excessively high, then an Fe chelate application can be made to the substrate.

Below are the options.

### *Iron Chelate Drench (options)*

- Iron-EDDHA: mix 5 ounces in 100 gallons of water
- Iron-DTPA: mix 5 ounces in 100 gallons of water
- Iron sulfate: mix 4-8 ounces in 100 gallons of water
- Apply as a substrate drench with sufficient volume to leach the pot.
- Rinse foliage immediately.
- Avoid use on iron efficient plants (geraniums).

## 3. Low EC Correction

If low EC problems occur, increase the fertilization rate to 300 ppm N for a few applications before returning to the recommend fertilization rate for the crop.

## 4. High EC Correction

Excessively high fertilization rates will result in a marginal leaf burn. Check the substrate EC to confirm your diagnosis. Values greater than 6.0 mS/cm based on the PourThru sampling method can be problematic for many plants.

### *Switch to Clear Water Irrigations*

If the substrate EC is just beginning to increase over time, then leach with a few clear water irrigations to lower EC levels by flushing out the salts.

### *Clear Water Leaching*

If the EC values are excessively high, leach the substrate twice with back-to-back clear water irrigations. Then allow the substrate to dry down normally before retesting the EC. If EC levels are still too high, repeat the double leach. Once the substrate EC is back within the normal range, use a balanced fertilizer at a rate of 150 to 200 ppm N.



**e-GRO Alert**

[www.e-gro.org](http://www.e-gro.org)

**CONTRIBUTORS**

Dr. Nora Cattlin  
Floriculture Specialist  
Cornell Cooperative Extension  
Suffolk County  
[nora\\_cattlin@cornell.edu](mailto:nora_cattlin@cornell.edu)

Dr. Chris Currey  
Assistant Professor of Floriculture  
Iowa State University  
[ccurrey@iastate.edu](mailto:ccurrey@iastate.edu)

Dr. Ryan Dickson  
Greenhouse Horticulture and  
Controlled-Environment Agriculture  
University of Arkansas  
[ryand@uark.edu](mailto:ryand@uark.edu)

Thomas Ford  
Commercial Horticulture Educator  
Penn State Extension  
[tf7@psu.edu](mailto:tf7@psu.edu)

Dan Gilrein  
Entomology Specialist  
Cornell Cooperative Extension  
Suffolk County  
[dog1@cornell.edu](mailto:dog1@cornell.edu)

Dr. Joyce Latimer  
Floriculture Extension & Research  
Virginia Tech  
[jlatime@vt.edu](mailto:jlatime@vt.edu)

Heidi Lindberg  
Floriculture Extension Educator  
Michigan State University  
[wolleage@anr.msu.edu](mailto:wolleage@anr.msu.edu)

Dr. Roberto Lopez  
Floriculture Extension & Research  
Michigan State University  
[rlopez@msu.edu](mailto:rlopez@msu.edu)

Dr. Neil Mattson  
Greenhouse Research & Extension  
Cornell University  
[neil.mattson@cornell.edu](mailto:neil.mattson@cornell.edu)

Dr. W. Garrett Owen  
Greenhouse Extension & Research  
University of Kentucky  
[wgowen@ukv.edu](mailto:wgowen@ukv.edu)

Dr. Rosa E. Raudales  
Greenhouse Extension Specialist  
University of Connecticut  
[rosa.raudales@uconn.edu](mailto:rosa.raudales@uconn.edu)

Dr. Beth Scheckelhoff  
Extension Educator - Greenhouse Systems  
The Ohio State University  
[scheckelhoff.11@osu.edu](mailto:scheckelhoff.11@osu.edu)

Dr. Ariana Torres-Bravo  
Horticulture/ Ag. Economics  
Purdue University  
[torres2@purdue.edu](mailto:torres2@purdue.edu)

Dr. Brian Whipker  
Floriculture Extension & Research  
NC State University  
[bwhipker@ncsu.edu](mailto:bwhipker@ncsu.edu)

Dr. Jean Williams-Woodward  
Ornamental Extension Plant Pathologist  
University of Georgia  
[jwoodwar@uga.edu](mailto:jwoodwar@uga.edu)

Copyright © 2021

Where trade names, proprietary products, or specific equipment are listed, no discrimination is intended and no endorsement, guarantee or warranty is implied by the authors, universities or associations.

**Cooperating Universities**

**Cornell CALS**  
College of Agriculture and Life Sciences

**Cornell Cooperative Extension  
Suffolk County**

**IOWA STATE UNIVERSITY**

**University of  
Kentucky**



**PennState Extension**

**VT VIRGINIA  
TECH**

**MICHIGAN STATE  
UNIVERSITY**

**UCONN**

**P PURDUE  
UNIVERSITY**



**College of Agricultural &  
Environmental Sciences  
UNIVERSITY OF GEORGIA**

**NC STATE  
UNIVERSITY**



**THE OHIO STATE  
UNIVERSITY**

**UofA DIVISION OF AGRICULTURE  
RESEARCH & EXTENSION**  
*University of Arkansas System*

**In cooperation with our local and state greenhouse organizations**

**MAUMEE VALLEY GROWERS**  
*Choose the Very Best.*



**Metro Detroit Flower Growers Association**

